




QuarkXPress 6.5 How-To...

Export a Print Ready PDF for Conventional Printing

There are no presets that can be defined for Quark 6.5, but a default can be set up by going to the QuarkXpress menu, selecting Preferences, then selecting the PDF tab and going into the Default Settings. All these settings can be set as a default then the only change that needs to be made when exporting to PDF is if the file has bleeds or not.

Use these screenshots as guides for exporting your files to PDF for Prinergy.



403 Brightseat Rd
Landover, MD 20785

301.499.9200

(toll free) 1.800.651.5050

(fax) 301.499.9304


www.corppress.com




QuarkXPress 6.5 How-To...

Export a Print Ready PDF for Conventional Printing

Feel free to fill in these fields, but they are not necessary.



Leaving these options to their default settings is fine.



403 Brightseat Rd
Landover, MD 20785
301.499.9200
(toll free) 1.800.651.5050
(fax) 301.499.9304
www.corppress.com



QuarkXPress 6.5 How-To...


Export a Print Ready PDF for Conventional Printing

Embed all fonts.

Do not Subset Fonts.

Set downsampling to 300 for images


Set downsampling to 1200 for bitmaps



Set output to "Composite DeviceN"

Check "Produce Blank Pages"

Set bleed to "0.125"




403 Brightseat Rd
Landover, MD 20785
301.499.9200
(toll free) 1.800.651.5050
(fax) 301.499.9304
www.corppress.com




QuarkXPress 6.5 How-To...

Export a Print Ready PDF for Conventional Printing

Do not use OPI



Do not use any profiles



403 Brightseat Rd
Landover, MD 20785
301.499.9200
(toll free) 1.800.651.5050
(fax) 301.499.9304
www.corppress.com